




When you open Radio Ra2 you will be prompted to create or open a project.

### 1. Select Create New Project




2. Go through the settings. I recommend under contact or technician information you place Nomad Groups information such as the below in the event a new company finds their way on it. Many jobs I inherited this would have been handy


3. You check off or create new rooms for the ones you need as seen below



4. You will now create Devices in specific rooms - you can label your rooms however you wish - wherever the equipment is actually located.



5. Select the device you would like to add. As you select Graffik Eye - you can see in the photo that it lets you set load type, zone name and etc here for each channel (tab around)



6. After adding devices - you will go to the program tab. You select the graffik eye button on left you want to program, and check the box next to the zone you wish to control with that button prompting you to select a fade rate and light level.

If you have a mylutron account then press the help menu at top and upgrade. You will be asked to sign into mylutron to generate a key for Radio Ra2 Inclusive. This upgrade will allow you to select "global scene" at bottom left drop down. I cannot remember the log in I used previously for this. BB may be able to help. Otherwise we will correct this at a later date. I recommend going to each graffik eye and checking their circuits for each button on the graffik eye programming in software. Basically this will cause every graffik eye to be controlled from each one, however the LED logic on the physical units will not track like they are all selecting Scene 1 as you are used to.

RadioRA 2 Essentials

design | **program** | activate | transfer

Longhorn Steakhouse 5186


Keypads | Timeclock

Selected Device Location:  
Equipment > Hallway

Selected Room: Equipment

Follow Device Location

**Hallway**




RF GRAFIK Eye QS

Zone 01 100% ☒ Local

Zone 02 50% ☒ Local

Zone 03 75% ☒ Local

**Other Hallway 2**



RF GRAFIK Eye QS

Zone 04 75% ☒ Local

Zone 05 50% ☒ Local


Zone 06 50% ☒ Local

Selected Button Type:  
Single / Multi-room scene [When to use](#)

Programmed Item Name	Level	Fade	
Equipment > Zone 01	100%	00:00:02	Delete
Equipment > Zone 02	50%	00:00:02	Delete
Equipment > Zone 05	50%	00:00:02	Delete
Equipment > Zone 06	50%	00:00:02	Delete
Equipment > Zone 04	75%	00:00:02	Delete
Equipment > Zone 03	75%	00:00:02	Delete

LUTRON  
Technical Support 1.800.523.9466

7. You will now go to the Activate tab. Press start activation. It will then find the main repeater and start pinging the graffik eyes. You should get instruction on what to do on screen as you do it  
First it will try and find the repeater, once it does you can change it's IP settings etc



8. After you have activated devices - you will be able to select the Transfer tab where you transfer your programming database to the main repeater. Once this is complete - be sure to save your database and send to BB and myself at least









